

GDA Test Automation

1.0 Purpose

GDA Test Automation is based on running a Javascript test script. In automation mode, GDA will run hands free and will execute each line in the test script one after the other.

The overall design of the test should do the following:

- (optional) Display the purpose of the test
- (optional) Display when the test starts
- Execute the steps in the test
- (optional) Display when the test has finished
- Set the test result (see `qgoproapp.testResult`)

2.0 Command line arguments

- `testscript` : path to the Javascript test script
- `testinterval` : interval in milliseconds between Javascript lines being executed
- `test log` : show test log window

Example command line usage:

```
<<GDAExe>> GoProLoginPlugin -testlog testscript "Tests/test1.js" -  
testinterval 2000
```

3.0 Reference: Triggering user interface events

Triggering user interface controls can be done with jquery. For example to trigger a click:

```
$(".GoProUIPlayerPlayButton").trigger("click");
```

The Class ID's for the Plugins will be published in a different document

3.1 safeQuery

`safeQuery` can be used instead of jquery `$ query`, if the query is empty then it will automatically exit with a test failure

Replace:

```
$(".GoProUIPlayerPlayButton").trigger("click");
```

With:

```
safeQuery(".GoProUIPlayerPlayButton").trigger("click");
```

4.0 Reference: GoProEditPlayer

GoProEditPlayer.getNumDroppedFrames

Purpose: Returns the number of playback dropped frames

Arguments: none

Return type: Integer

Example usage:

```
var numDropFrames =
```

```
GoProEditPlayer.getNumDroppedFrames();
```

GoProEditPlayer.toggleFullScreenPlayer

Purpose: Toggle player between full screen and regular

Arguments: none

Return type: none

Example usage:

```
GoProEditPlayer.toggleFullScreenPlayer();
```

GoProEditPlayer.GetNormalizedPlayheadLocation

Purpose: Returns the normalized play head location

Arguments: none

Return type: Double

Example usage:

```
var numDropFrames =
```

```
GoProEditPlayer.GetNormalizedPlayheadLocation();
```

5.0 Reference: qgoproapp

qgoproapp.setTestMediaSourceFile

Purpose: sets the test media footage for player

Arguments: #1 file name (string)

Return type: none

Example usage:

```
qgoproapp.setTestMediaSourceFile("/path/to/media.mp4");
```

qgoproapp.setTestWatchFolder

Purpose: sets the watch folder

Arguments: #1 folder name (string)

Return type: none

Example usage:

```
qgoproapp.setTestWatchFolder("/path/to/watch");
```

qgoproapp.setTestOffloadFolder

Purpose: sets the offload folder

Arguments: #1 folder name (string)

Return type: none

Example usage:

```
qgoproapp.setTestOffloadFolder("/path/to/offload");
```

qgoproapp.showTestMessage(message)

Purpose: show a message in the overlay

Arguments: #1 message (string)

Return type: none

Example usage:

```
qgoproapp.showTestMessage("Test starting");
```

qgoproapp.setTestTimerInterval(msecs)

Purpose: sets the number of milliseconds to wait between each command that is executed

Arguments: #1 interval in milliseconds (integer)

Return type: none

Example usage:

```
qgoproapp.setTestTimerInterval(4000);
```

qgoproapp.testResult(result, passMessage, failMessage)

Purpose: sets the overall test result, either pass or fail

Arguments: #1 success flag (bool)

#2 pass message (string)

#3 failMessage (string)

Return type: none

Example usage:

```
qgoproapp.testResult(numDrops < 10, "Dropped frames = " +  
numDrops.toString() + " < 10", "Dropped frames = " +  
numDrops.toString());
```

qgoproapp.executeTestProcess(execPath, arguments)

Purpose: executes a process command

Arguments: #1 name of executable to process (string)

#2 Array list of string for command arguments

Return type: none

Example usage:

```
var returnCode = goproapp.executeTestProcess("/path/  
imgtest", ["file1.png", "file2.png"]);
```

qgoproapp.saveWindowPositionSettings()

Purpose: Store the position and size of the application window

Arguments: none

Return type: none

Example usage:

```
qgoproapp.saveWindowPositionSettings();
```

qgoproapp.windowMaximize()

Purpose: Maximize the application window

Arguments: none

Return type: none

Example usage:

```
qgoproapp.windowMaximize();
```

qgoproapp.windowMinimize()

Purpose: Minimize the application window

Arguments: none

Return type: none

Example usage:

```
qgoproapp.windowMinimize();
```

qgoproapp.restoreWindowPositionSettings()

Purpose: Restore the position and size of the application window

Arguments: none

Return type: none

Example usage:

```
qgoproapp.restoreWindowPositionSettings();
```

qgoproapp.quitApp()

Purpose: Quit application

Arguments: none

Return type: none

Example usage:

```
qgoproapp.quitApp();
```

qgoproapp.waitForTest

Purpose: wait for a number of milliseconds

Arguments: #1 number of milliseconds (integer)

Return type: none

Example usage:

```
qgoproapp.waitForTest(2000);
```

qgoproapp.pauseTest

Purpose: pause the test or continue

Arguments: #1 pause test (bool)

Return type: none

Example usage:

```
qgoproapp.pauseTest(someCondition);
```

qgoproapp.gotoTestLabel

Purpose: jump the test to the line with the label

Arguments: #1 label name (string)

Return type: none

Example usage:

```
qgoproapp.gotoTestLabel("start_loop");
```

qgoproapp.executeTestProgram

Purpose: executes an entire test program

Arguments: #1 file name (string)

Return type: none

Example usage:

```
qgoproapp.executeTestProgram("/path/to/program.js");
```

6.0 Example scripts

6.1: Playback frame drop test

```
qgoproapp.showTestMessage("Playback Frame Testing ...
starting...");
qgoproapp.setTestMediaSourceFile("/Users/sukendeepsamra/
Desktop/Media/LemonsHD.mp4");
safeQuery(".GoProUIPlayerSourceButton").trigger("click");
var numDrops = GoProEditPlayer.getNumDroppedFrames();
safeQuery(".GoProUIPlayerPlayButton").trigger("click"); //
Play
qgoproapp.waitTest(20000); // Wait 20 seconds
safeQuery(".GoProUIPlayerPlayButton").trigger("click"); //
Stop
qgoproapp.showTestMessage("Playback Testing ... analysing
results...");
numDrops = GoProEditPlayer.getNumDroppedFrames() -
numDrops;
qgoproapp.testResult(numDrops < 10, "Dropped frames = " +
numDrops.toString() + " < 10", "Dropped frames = " +
numDrops.toString());
safeQuery(".GoProUIPlayerBackButton").trigger("click"); //
Go to Media Library
qgoproapp.quitApp();
```

6.2: Maximize window test

```
qgoproapp.showTestMessage("Maximize Window Testing ...
starting...");
qgoproapp.setTestMediaSourceFile("/Users/sukendeepsamra/
Desktop/Media/LemonsHD.mp4");
safeQuery(".GoProUIPlayerSourceButton").trigger("click");
safeQuery(".GoProUIPlayerPlayButton").trigger("click"); //
```

```

Play
qgoproapp.saveWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
safeQuery(".GoProUIPlayerPlayButton").trigger("click"); //
Stop
safeQuery(".GoProUIPlayerBackButton").trigger("click"); //
Go to Media Library
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
safeQuery(".GoProUILoginButton").trigger("click"); // Go to
Login
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.windowMaximize();
qgoproapp.restoreWindowPositionSettings();
qgoproapp.showTestMessage("Maximize Window Testing ...
analysing results...");
qgoproapp.testResult(true, "not crashed", "");
qgoproapp.quitApp();

```

6.3: Other Example Test Scripts

```

Example 1 - GUMI API
Example 2 - jQuery / Double Click Event
Example 3 - jQuery / Context Menu
Example 4 - Auto Comp Test
Example 5 - Events / pauseTest
Example 6 - Loop Testing
Example 7 - Execute JS Program
Example 8 - Watch Folder

```

